Nov 2023

## Introduction

There are occasions where we might want to assign multiple network addresses to a single interface on a server. This might be because you want to talk to another network where no routing exists, or you might want to assign a second address to a server where the main IP Address cannot be changed (maybe changing the primary management address will break the unit).

This article is written with the assumption that you are using on prem hardware, not sure if this has any suitability in cloud environments.

There are a couple of methods we can discuss here, there is what I would call a quick and dirty method, that has some limitations, and there is a better method of doing this, it takes a little more work, but it worth the effort in the long run.

## **Quick and Dirty Method**

If you just need a second IP Address because the existing one is not suitable (and cannot be changed because maybe it will break the software) then you can use this method.

Lets look at an existing configuration for the first interface, which is normally the management interface on eno1 (or eth0 for CentOS if you have used the MediaKind ISO for OS install).

In Alma/CentOS/RedHat the interface configuration files are stored in /etc/sysconfig/network-scripts. In this example there are two interfaces, eno1 and eno2. eno1 is for management and eno2 is for data.

If we look at the interface configuration, we can see the IP Addresses available on each interface.

ip -br -c a		
lo	UNKNOWN	127.0.0.1/8
eno1	UP	192.168.1.223/24
eno2	UP	11.0.223.2/16

We can see that the interface enol currently has a single IP Address of 192.168.1.233. However, lets assume that we want to add an additional IP Address of 10.32.13.233.

Here is the current configuration of eno1 where we only have a single IP Address of this interface.

TYPE=Ethernet PROXY\_METHOD=none BROWSER\_ONLY=no DEFROUTE=yes IPV4\_FAILURE\_FATAL=no IPV6INIT=yes IPV6 AUTOCONF=yes IPV6 DEFROUTE=yes IPV6 FAILURE FATAL=no NAME=eno1 UUID=ca90417f-9df9-4f34-bae5-77aa6531cc00 DEVICE=eno1 ONB00T=yes IPADDR=192.168.1.223 PREFIX=24 GATEWAY=192.168.1.1 PREFIX1=24 DNS=8.8.8.8

We can edit this file and simply add another address to this interface, if we edit this file we can add these lines to the ifcfg-eno1 file:

Last update: 2023/11/13 multiple\_ip\_addresses\_on\_single\_interface http://cameraangle.co.uk/doku.php?id=multiple\_ip\_addresses\_on\_single\_interface&rev=1699895107 17:05

IPADDR1=10.32.13.223 PREFIX1=24 DNS1=8.8.4.4 (this line is not required, it just shows we can add another DNS setting.

Below is the edited ifcfg-eno1 configuration file with the additional lines (in Blue).

TYPE=Ethernet PROXY METHOD=none BROWSER ONLY=no DEFROUTE=ves IPV4 FAILURE FATAL=no IPV6INIT=yes IPV6 AUTOCONF=yes IPV6 DEFROUTE=yes IPV6 FAILURE FATAL=no NAME=eno1 UUID=ca90417f-9df9-4f34-bae5-77aa6531cc00 DEVICE=eno1 ONBOOT=ves IPADDR=192.168.1.223 PREFIX=24 GATEWAY=192.168.1.1 PREFIX1=24 DNS=8.8.8.8 IPADDR1=10.32.13.223 PREFIX1=24 DNS1=8.8.4.4

If we look at the interface details in the OS now we can see the following IP Addresses.

eno1 UP 192.168.1.223/24 10.32.13.223/24

We can see that the interface has two IP Addresses. The big issue with this method is the Gateway, the first IP Address has the gateway (192.168.1.1) where as the 10.32.13.233 has no gateway. We could change the gateway to accommodate the new additional IP, but I don't believe you can have two gateways. I have not tried to add a second gateway, but I believe that method two would be preferential as this is really a quick method.

## **The Better Method**

The better method requires using multiple configuration files for a single interface. This method has a couple of advantages, it simplifies adding addresses and allows for multiple gateways to be used.

In the directory /etc/sysconfig/network-scripts we can see in this example we two interfaces:

-rw-r-r-. 1 root root 255 Nov 13 17:01 ifcfg-eno1 -rw-r-r-. 1 root root 232 Nov 13 17:00 ifcfg-eno2

ifcfg-enol is the interface that we want to apply multiple IP Addresses to. Firstly we will copy this interface file and edit each file accordingly. When creating the new interface configuration files we will add a number to the end of each file:

cp ifcfg-eno1 ifcfg-eno1:0 cp ifcfg-eno1 ifcfg-eno1:1

TYPE=Ethernet PROXY\_METHOD=none BROWSER\_ONLY=no DEFROUTE=yes IPV4\_FAILURE\_FATAL=yes NAME=eno1 UUID=ca90417f-9df9-4f34-bae5-77aa6531cc00 DEVICE=eno1 ONBOOT=yes IPADDR=192.168.1.223 PREFIX=24 GATEWAY=192.168.1.1 BOOTPROTO=none IPV6\_DISABLED=yes IPV6INIT=no

From: http://cameraangle.co.uk/ - WalkerWiki - wiki.alanwalker.uk

Permanent link: http://cameraangle.co.uk/doku.php?id=multiple\_ip\_addresses\_on\_single\_interface&rev=1699895107 Last update: 2023/11/13 17:05

WalkerWiki - wiki.alanwalker.uk - http://cameraangle.co.uk/