


# A quick note on the Mongo Arbiter

May 2020

## Introduction

There is a page dedicated to the Arbiter (on Windows) [here](#) but I wanted to separately address an issue here.

Below we can see an nCompass map with 1+1 MKSP running active/standby.



From this we can deduce that SP01 is the active mux, and so we can safely reboot SP02 right? well, no, not exactly. and the reason for this is Mongo.

Look at the image below:

```
[root@sp01 ~]# ip a show eth0
2: eth0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast state UP group default qlen 1000
    link/ether 00:e0:f4:2d:62:07 brd ff:ff:ff:ff:ff:ff
    inet 192.168.1.203/24 brd 192.168.1.255 scope global noprefixroute eth0
        valid_lft forever preferred_lft forever
    inet6 fe80::2e0:f4ff:fe2d:6207/64 scope link
        valid_lft forever preferred_lft forever
[root@sp01 ~]#
```

```
[root@sp02 ~]# ip a show eth0
2: eth0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast state UP group default qlen 1000
    link/ether 00:e0:f4:2d:61:38 brd ff:ff:ff:ff:ff:ff
    inet 192.168.1.204/24 brd 192.168.1.255 scope global noprefixroute eth0
        valid_lft forever preferred_lft forever
    inet 192.168.1.214/32 scope global eth0
        valid_lft forever preferred_lft forever
    inet 192.168.1.213/32 scope global eth0
        valid_lft forever preferred_lft forever
    inet6 fe80::2e0:f4ff:fe2d:6138/64 scope link
        valid_lft forever preferred_lft forever
[root@sp02 ~]#
```

This is two SSH sessions to the two MKSP units (SP01 on the left, SP02 on the right). To get this information use **ip a show eth0** on both SP SSH sessions.

It can be seen that while SP01 is the active Mux on the map, SP02 has the VIP for Management and the VIP for Licensing. Of course these can be taken over by SP01, but not without some delay (the Mongo Arbiter has to sort this out).

However, even if The primary mux in nCC is SP01, and the management and licensing VIP are on SP01, there is another element to consider.

From the SSH sessions to Mux SP01 and SP02, enter the following:

```
mongo
```

Looking at the output below, we can see that the Primary Mongo instance is on SP02, and the Secondary Mongo instance is on SP01.

```
[root@sp01 ~]# mongo
MongoDB shell version v4.0.15
connecting to: mongodb://127.0.0.1:27017/?gssapiServiceName=mongodb
Implicit session: session { "id" : UUID("ba6ff146-96e1-4c44-bf92-d63581e2944e") }
MongoDB server version: 4.0.15
repldb:SECONDARY>
```

```
[root@sp02 ~]# mongo
MongoDB shell version v4.0.15
connecting to: mongodb://127.0.0.1:27017/?gssapiServiceName=mongodb
Implicit session: session { "id" : UUID("d9a56fa1-dbfc-4bd2-b8e1-6a6dc9c48a50") }
MongoDB server version: 4.0.15
repldb:PRIMARY>
```

This means that rebooting the nCC inactive mux (SP02) could have consequences as it is the Mongo primary (database primary). This is only an issue at the time of writing, and hopefully will not be so much an issue in the future, but it is still worth knowing what you are rebooting.

Last update: 2023/03/09  
22:35

a\_quick\_note\_on\_the\_mongo\_arbiter [http://cameraangle.co.uk/doku.php?id=a\\_quick\\_note\\_on\\_the\\_mongo\\_arbiter](http://cameraangle.co.uk/doku.php?id=a_quick_note_on_the_mongo_arbiter)

---

From:

<http://cameraangle.co.uk/> - WalkerWiki - [wiki.alanwalker.uk](http://wiki.alanwalker.uk)

Permanent link:

[http://cameraangle.co.uk/doku.php?id=a\\_quick\\_note\\_on\\_the\\_mongo\\_arbiter](http://cameraangle.co.uk/doku.php?id=a_quick_note_on_the_mongo_arbiter)

Last update: **2023/03/09 22:35**

