

MFEL Logs

July 2018

When looking at logs, the first thing to remember is that you could be dealing with an Appliance (so Controller and 'Product' on a single server, or Controller on Server A and Product on Server B, C etc.) This will be different again for uService based systems.

If you have an appliance, then all logs in will on the appliance itself, that is quite easy. For distributed systems, you have to find the appropriate log on the appropriate server, the location however will be the same.

Most of the logs seem to be in `/var/log/ericsson` so for example, the MFEL logs for Encoding Live will be in `/var/log/ericsson/encoding-live-worker/private`.

Here is a sample set of log files:

```
cleanFiles.log
cleanFiles.log-20180629.gz
cleanFiles.log-20180630.gz
cleanFiles.log-20180701.gz
cleanFiles.log-20180702.gz
cleanFiles.log-20180703.gz
config-daemon-alarm.log
config-daemon.log
config-daemon.log-20180629.gz
config-daemon.log-20180703.gz
config-daemon-worker.log
liveencoder_daemon-2.11.2-trace-d8fe7b99087a4d0eaf07f91ba18c1c60-mfel01.log
liveencoder_daemon-2.11.2-trace-d8fe7b99087a4d0eaf07f91ba18c1c60-mfel01.log-20180630.gz
liveencoder_daemon-2.11.2-trace-d8fe7b99087a4d0eaf07f91ba18c1c60-mfel01.log-20180703.gz
liveencoder_daemon-2.11.2-trace-.log
liveencoder_daemon-2.11.2-trace-.log-20180629.gz
liveencoder_daemon-2.11.2-trace-mfel01.log
liveencoder_daemon-2.11.2-trace-mfel01.log-20180629.gz
liveencoder_daemon-2.11.2-trace-mfel01.log-20180703.gz
liveTranscoder_d8fe7b99087a4d0eaf07f91ba18c1c60_6c70bdab-b03f-1a3a-45ab0b17-37939268.dmp
liveTranscoder_d8fe7b99087a4d0eaf07f91ba18c1c60_6c70bdab-b03f-1a3a-45ab0b17-37939268.dmp-20180630.gz
liveTranscoder_d8fe7b99087a4d0eaf07f91ba18c1c60_6d67f16b-0022-924a-0a4c2f4d-777f6e40.dmp
liveTranscoder_d8fe7b99087a4d0eaf07f91ba18c1c60_6d67f16b-0022-924a-0a4c2f4d-777f6e40.dmp-20180630.gz
liveTranscoder_d8fe7b99087a4d0eaf07f91ba18c1c60-alarm-mfel01.log-20180630.gz
liveTranscoder_d8fe7b99087a4d0eaf07f91ba18c1c60-trace-continuityCounters-mfel01.log
liveTranscoder_d8fe7b99087a4d0eaf07f91ba18c1c60-trace-continuityCounters-mfel01.log-20180630.gz
liveTranscoder_d8fe7b99087a4d0eaf07f91ba18c1c60-trace-continuityCounters-mfel01.log-20180701.gz
liveTranscoder_d8fe7b99087a4d0eaf07f91ba18c1c60-trace-continuityCounters-mfel01.log-20180702.gz
liveTranscoder_d8fe7b99087a4d0eaf07f91ba18c1c60-trace-continuityCounters-mfel01.log-20180703.gz
liveTranscoder_d8fe7b99087a4d0eaf07f91ba18c1c60-trace-graphMonitor-mfel01.log-20180630.gz
liveTranscoder_d8fe7b99087a4d0eaf07f91ba18c1c60-trace-highLevel-mfel01.log-20180630.gz
liveTranscoder_d8fe7b99087a4d0eaf07f91ba18c1c60-trace-mfel01.log
liveTranscoder_d8fe7b99087a4d0eaf07f91ba18c1c60-trace-mfel01.log-20180630.gz
liveTranscoder_d8fe7b99087a4d0eaf07f91ba18c1c60-trace-mfel01.log-20180701.gz
liveTranscoder_d8fe7b99087a4d0eaf07f91ba18c1c60-trace-mfel01.log-20180702.gz
liveTranscoder_d8fe7b99087a4d0eaf07f91ba18c1c60-trace-mfel01.log-20180703.gz
liveTranscoder_d8fe7b99087a4d0eaf07f91ba18c1c60-trace-tsMux-mfel01.log-20180630.gz
```

From:
<http://cameraangle.co.uk/> - WalkerWiki - wiki.alanwalker.uk

Permanent link:
http://cameraangle.co.uk/doku.php?id=mfel_logs

Last update: 2023/03/09 22:35

